PDSEGEN Reference Card

Primary Commands			
Command	Description		
<u>BAC</u> KUP	Backup PDSE V2 member generations		
B ROWSE member	Browse member		
C dsn filter	Change to another PDSE, with mbr filtering		
COPY dsn	Copy to a PDSE		
<u>E</u> DIT member	Edit member		
<u>FIL</u> TER	Member list filtering		
<u>F</u> IND text	Find a text string in member name or data		
<u>G</u> ENONLY	Only non-0 generations		
<u>H</u> IDE	Only 0 generations		
<u>HIG</u> EN	Information on deleted members		
<u>I</u> NFO	Dataset summary information		
<u>L</u> OCATE text	Locate text string		
MOD EL	Allocate new PDSE with same attributes		
<u>MONTH</u>	Members changed in last 30 days		
<u>OP</u> TIONS	Display and execute all primary commands		
<u>OUT</u> PUT	Write member list to dataset		
<u>P</u> RUNE	Delete all non-generation members		
REFRESH or RESET	Rebuild member list		
<u>REST</u> ORE	Restore members from backup DSN		
TODAY	Members changed today		
<u>VA</u> LIDATE	Validate PDSE dataset		
<u>WEEK</u>	Members changed in last 7 days		
<u>V</u> IEW member	View member		
YEAR	Members changed this year		

Line Commands			
Command	Only	Description	
Α	Zero	Attribute of member	
В		Browse member	
C or COP	Zero	Copy member, with generations	
D		Delete member	
E	Zero	Edit member	
G or REC	Non-Zero	Recover a generation to a new member	
Н		Hide member	
1		Information on member	
J		Submit member	
K	Zero	Copy member	
M		Mail member	
0		Options	
P	Non-Zero	Promote non-zero generation to zero	
Q or RENS	Zero	Swap two member names and gens	
R or REN	Zero	Rename member	
S		Select member (B, E or V)	
U		Enter user command	
V		View member	
X		Execute member	
Z or COM	Non-Zero	Compare non-zero generation to zero	

Comments			
Primary Commands	Line Commands		
Primary command characters <u>underlined</u> and bold signify abbreviation	Placing the cursor on a row and pressing ENTER will select the member		
Wild cards (% and *) can be specified in the member name	Line commands can be blocked or numeric, example: DD-DD or D9999		
Type LEFT (F10) or RIGHT (F11) to display different columns	The 'Status' field allows typing in a member name for some commands		
Type HELP (F1) to display tutorials	Several line commands can be typed in at once		