## Product Launch Point (PLP) The Dynamic ISPF Menu Tool – Installation Guide

| Product Launch Point (PLP) The Dynamic ISPF Menu Tool – Installation Guide |  |
|--|--|
| Overview   |  |
| Installation and Customization   |  |

## **Overview**

This is the installation and customization guide for the Product Launch Point (PLP) application.

## Installation and Customization

The installation consists of copying the PLP elements into the correct libraries:

| REXX EXECs  |                                  | copy into a library in your SYSPROC or SYSEXEC    |
|-------------|----------------------------------|---|
| PLPISPF     | the PLP application              | concatenation in the TSO LOGON PROC               |
| PLPEDM      | ISPF Edit Macro used in creating |   |
|             | the information member           |   |
| ISPF Panels |                                  | copy into a library in your ISPPLIB concatenation |
| PLPADM      | Admin Panel                      | in the TSO LOGON PROC                             |
| PLPADMA     | Admin Panel (short)              |   |
| PLPADMDD    | Additional Dataset entry         |   |
| PLPADME     | Change/Insert Applications       |   |
| PLPADMEU    | Change/ Application (short)      |   |
| PLPADMU     | Change Application for User      |   |
| PLPBR       | Browse Panel                     |   |
| PLPDSPE     | Display table entry              |   |
| PLPDSPEU    | Display table entry (short)      |   |
| PLPGPOP     | Group DSN Popup                  |   |
| PLPLIST     | Default Table Display Panel      |   |
| PLPH0       | Help for PLPLIST                 |   |
| PLPHL       | Help for Launch option           |   |
| PLPMHA      | Help for Alias                   |   |
| PLPMH0      | Help for PLPADM                  |   |
| PLPMH1      | Help for PLPADME                 |   |
| PLPMHE      | Help for PLPADMDD                |   |

In the PLPISPF REXX EXEC customize the following variables (do a find for \*custom\*):

| plpispf_table | the name of the partitioned dataset which will be used for the PLP Tables and for the information |
|---------------|---|
|               | members   |
| racf_groups   | The default RACF group names that are allowed   |
|               | ADMIN capabilities.   |
| save_limit    | the number of backup copies of the PLP Table to   |
|               | save  |
| steplib       | Define which dynamic STEPLIB command will be  |
|               | used, if any.   |
| tbsort        | Determines the sort order for the table. If set to 0  |
|               | then the table will sort with application names   |
|               | sorted in alphanumeric order. If set to 1 (the default)   |
|               | the table will sort with numeric entries first.   |

Update either the ISPF Command Table ISPCMDS or the site ISPF Commands Table to include the following entries:

```
Verb T Action

Description

'''' PLP 0 SELECT CMD(%PLPISPF &ZPARM) SCRNAME(PLP) NEWAPPL(PLP)

Product Launch Point

'''' PLPS 0 SELECT CMD(%PLPISPF /SYS &ZPARM) SCRNAME(PLP) NEWAPPL(PLP)

Product Launch Point for Systems

'''' PLPU 0 SELECT CMD(%PLPISPF /USER &ZPARM) SCRNAME(PLP) NEWAPPL(PLP)

Product Launch Point for Users

'''' RFIND 0 &USRRFIND

Repeat Find (Rfind) Controlled Passthru
```

Another installation option is to add an option to the ISPF Primary Options Menu similar to that shown in below.

```
Z ZipTo Fastpath to Application via User List
```

This allows the user to enter **Z**.xxx, where xxx is the application name in the User application list. Thus **Z.ST**, in our example, would start the **SDSF** Status dialog.

The updates to the panel would include that line plus the following statements in the )PROC section:

Insert before the &ZSEL statement:

```
&ZCMD = TRUNC(&ZCMD,'.')
&ZTRAIL=.TRAIL
```

Insert after the &ZSEL statement appropriately:

```
Z,'CMD(%plpispf /user &ztrail) Newappl(PLP)'
```